



HVY16 Cadillac SPECIAL SAUCE

Drain to Waste

- Change reservoir every 7 days
- Keep pH between 5.8 - 6.1 for Hydro or Soiless media. For Soil Keep pH between 6.2-6.6. Keep Water Temp at 66-68 F.
- Add MagiCal to Fresh Purified Water and bring up to 40 ppms for first 4 weeks of Bloom
- Only add additives whenever you change out reservoir
- Add Nutrient up to Desired TDS level

Reservoir Maintenance

- Add all Additives first (follow directions below)
 - MagiCal**- Add to RO Water. 30-40ppms before other additives. Only Veg. and first 4 weeks of Bloom.
 - Big Bud and Overdrive** - 100ppms - use as directed from recipe sheet. Never both at same time.
 - Vermi-T**- Live Worm/Compost Tea w/30,000 Microbes! - 1 Gallon for 50 Gallon Reservoir.
 - Cannazym** - Use 2-4 tsp. / Gal.Strongest Digestive Enzyme on the Market.
 - Roots Excelerator** - Blows Roots way out. Awesome product! - 1.1mL per Gallon. Use every other week.
 - Roots Bloom** - 1/2tsp. / Gal. Alternate with Roots Excel. Every other week. Keeps Roots Healthy!
 - Voodoo Juice** - 1-2 tsp. / Gal. Bacteria and Protozoa Mix. Creates very strong and Large Root Zone.
 - Piranha** - 0.75 Grams per Gallon - Mychorrizae and Trichoderma Fungi. Simply Amazing!
 - Hygrozyme** - 2tsp/Gal thru week 4 of Bloom. Growth promoting enzymes. More, faster, greener growth.
 - Budswel** - 3tsp/Gal weeks 2-5 of Bloom. 6tsp/Gal weeks 6-8 of Bloom. Gives you that taste you crave.
 - Pre Bloom** - 1 tsp./Gal. Use in weeks 2-3 of Veg. Gives thicker stalks, more brances, more bloom sites.
 - Ultra Bloom** - 1 tsp./Gal. Use in weeks 1-2 of Bloom. Increases initial flower set. Triggers bloom faster.
 - Ooze Bloom** - 1 tsp./Gal. Use in weeks 4-6 of Bloom. Develops more Mass and adds oil/sugar to fruit.
 - Silica Bloom** - use as ph up. Increases cell wall integrity. Plants yield more. More resistant to disease.
 - Bud Candy** -1-3tsp./Gal. Food for Microbes) Also will promote for Oil, Resin, Sugar.
 - Grand Finale** - 4tsp/Gal week 7 of bud. 2tsp/Gal week 8 of Bloom. Finishes with Flavor and Color!
 - Purple Maxx** - Follow Special Instructions - 1tsp. / Gal. for weeks 7 and 8. (5mL/Gallon) **Foliar**-5mL/Qt.
 - Final Phase** - 2tsp. per Gallon. (10mL/Gallon)
- Now add your nutrient to the desired TDS (ppm). *If the concentration is ever too high - dilute with water.*
- Check and adjust pH. ALWAYS pH - even when not mentioned!
- Make sure to have air stones in reservoir. O2 is more important than Additives. More aeration is better.
- Make sure water temp is 66-68 deg. F. (More oxygen is available at cooler temperatures.)

Other Maintenance

- A general recipe for Soil, Soiless, or Hydro Based Mediums. *The pH listings are for Hydro or Soiless Media.*
- If running in **Soil** (which this recipe works GREAT for), then make sure to adjust the **pH to 6.5 on Average.**
Soil pH can fluctuate between 6.2 and 6.6.
- Make sure you have great drainage in trays/pots. No roots sitting in standing water!
- Additives should not equal more than 33% of your overall TDS (ppms.) Ex. 1200 ppms - Additives should not be more than 400 ppms at the most. Additives are anything except Main nutrient 2 Part.
- Check for Nutrient burn. If you see leaf tips yellow/browning or burning on edges of leaves, lower your Overall TDS values. Do not let plants get necrotic spotting in the middle of leaves. If you see any serious burning - FLUSH reservoir and re-do nutrients at 200 ppm lower than before.
- Always look for signs of overwatering - Plants get heavy saggy look and feel to them. Adjust water timer.
- Any time you do a FLUSH check to see what your "Run-Off" pH and (ppms) come out at. A healthy medium will have the same pH & ppms as the water you are putting in. Call with Questions.!

• 3560 STATE STREET	• 2405 MIRA MAR AVE.	• 496 W. MEATS ST.	• 11510 WHITTIER BLVD.	• © 2009 GCH, INC.
• SANTA BARBARA, CA 93105	• LONG BEACH, CA 90815	• ORANGE, CA 92865	• WHITTIER, CA 90601	• www.gchydro.com
• PHONE: 805.898.9922	• PHONE: 562.627.5636	• PHONE: 714.974.4769	• PHONE: 562.699.4201	• info@gchydro.com
• FAX: 805.898.0047	• FAX: 562.627.1618	• FAX: 714.921.4769	• FAX: 562.699.7598	• TOLL FREE: 877.MY.HYDRO
				69 49376



Seedlings or Cuttings:

Use **SensiGro A+B** (for main nutrient)

If starting from seed you will want to build your TDS up. You will start at 300-400 ppms after the seed cracks. To crack the seed soak in warm water between a damp paper-towel for a couple of days. Once cracked, move to **Ready Grow** cube. You will bring TDS up 200 or so ppms per week until at 1000-1200ppms for Bloom.

Note: **Piranha, Vermi-T, Voodoo Juice, Hygrozyme & Roots Excelerator** are all good. (After first roots developed.)

If Using **Rooted Cuttings**, you will want to start your clones at the same TDS that the parents were kept at. If you do not know what that level was, a safe place to start is 800 - 1000 ppms. You will be looking for new growth on the tops of the plant before we can safely put them into the vegetative stage.

Note: One of the major problems people have with cuttings is that they throw them under too intense of a light source. Clones are coming from an area with a low intensity of light and extremely humid conditions. Make sure your HID light is high at first and lower it 6" a day until desired height is reached. Also spray plants occasionally with **Alg-A-Mic**, and combined with a wetting agent like **Wet Betty**.

Vegetative Stage:

Use **Heavy 16 Grow A + B** Nutrient

If starting from seed - you will raise your ppms up to 1000-1200 ppms throughout this phase. You will want to start at 300-400 ppms. For the first 2 weeks you will coddle your plants and tend to their every desire. You will then raise the ppms 200 per week. Look to see if there is any damage at all to their leaves. If yes, lower the TDS! Steadily raise ppms every week until you get to 1000-1200 ppms. You should be able to follow the Bloom chart/map in this hand-out. You may have to start week 1 at 1100 instead of 1200. If this is the case, raise ppms 100 every week until you get to 1500 in week 5 (instead of week 4.)

If starting from Rooted Clone - You will want to keep your plants in the 1000 ppm - 1200 ppm range for this entire cycle. No Higher levels needed. Yes. You can start at 800 -1000ppms! Because thats where parent was. Before adding Nutrient.

Add Each of your desired additives.

Now add Nutrient to desired TDS (ppms).

You will want to maintain your **pH** at **5.8 - 6.1** for Hydro or Soilless. For Soil Maintain **ph** at **6.2-6.6**.

Here is an example of a 3 week vegetative schedule (starting from cuttings/clones of your favorite plant(s))

Week 1 - TDS 700 (Fresh Reservoir) (**Bud Candy** at 1tsp./Gal. *Food for Microbes / more sugar in plant*).

Connect Air Stones to Air Pump and submersesstones in Water. Make Sure they work.

Check Timer for Pump, and set appropraite on/off times; depending on system type and grow media used.

Make Sure Tray(s) / Pots Drain.

Start Your Reservoir by adding **Reverse Osmosis (RO) water**.

Add MagiCal up to 30 ppm.

Next Add Additives. (**Roots Excelerator, Vermi-T, Voodoo Juice, Piranha, Bud Candy, Hygrozyme.**)

Now add **Heavy 16 A+B Grow** - bring TDS to 800 ppms. Adjust daily- keep at 800 ppms all week.

Adjust pH to 5.8-6.1 (Play with **pH** - between **5.8-6.1 for Hydro/Coco**). For Soil pH should be 6.5

Check water temp after 1-2 days Make sure it is bewteen 66-68 deg. F. This is important to get right Now!

Week 2 - TDS 950 (Same steps as Week 1 - New TDS) (**Pre Bloom** is in for this week at 1tsp./Gal.)

Fill and Dose Reservoir. Make sure Reservoir temperature is between 66-68 deg. F.

Add MagiCal up to 30 ppms.

Next Add Additives. (**Roots Bloom, Vermi-T, Piranha, PreBloom, Bud Candy, Voodoo Juice, Hygrozyme.**)

Now add **Heavy 16 A+B Grow** - bring TDS to 800 ppms. Adjust daily- keep at 800 ppms all week.

Adjust **pH to 5.8-6.1** (keep pH at level you found to be right last week.) Soil pH should be btwn 6.2-6.6.

Keep levels of pH and TDS correct. Make sure you have good drainage!

Now is the time to figure out and dial in your mediums water needs. You will want to make sure that your given medium (Coco/ Soilless / Rockwool) goes from WET to BARELY MOIST before you water again. This is critical to get right now.

: 3560 STATE STREET

: SANTA BARBARA, CA 93105

: PHONE: 805.898.9922

: FAX: 805.898.0047

: 2405 MIRA MAR AVE.

: LONG BEACH, CA 90815

: PHONE: 562.627.5636

: FAX: 562.627.1618

: 496 W. MEATS ST.

: ORANGE, CA 92865

: PHONE: 714.974.4769

: FAX: 714.921.4769

: 11510 WHITTIER BLVD.

: WHITTIER, CA 90601

: PHONE: 562.699.4201

: FAX: 562.699.7598

: © 2009 GCH, INC.

: www.gchydro.com

: info@gchydro.com

: TOLL FREE: 877.MY.HYDRO

69 49376



FLUSH - Use RO Water. Make sure water comes out clean. "From Dirty to Clean"

Week 3 - TDS 1100

Start Your Reservoir by adding **RO water** Check water temp - make sure it is between 66-68 deg. F. Connect Air Stones to Air Pump and submerge Stones (Not Pump!) in Water, Making Sure Stones work. Add MagiCal up to 30 ppm.

Next Add Additives. (**Roots Excelsator, Vermi-T, Voodoo Juice, Piranha, Hygrozyme, and Bud Candy**).

Now add **Heavy 16 A+B Grow** - bring TDS to 800 ppms. Adjust daily- keep at 800 ppms all week.

Adjust **pH** to **5.8-6.1** (You will have to play with pH - between 5.8-6.1. Soil pH should be btwn 6.2-6.6.

Make Sure Tray(s) / Pots Drain. Make sure you **CONNECT** Irrigation PUMP to timer and it is ON!

Fruit/Flower Stage:

Use **Heavy 16 BUD A + B Nutrient**. Start w/ **pH 5.8(For hydro or Soiless.) (6.5 pH for Soil!)**

Add **Piranha** (.75gram / Gal,)**Voodoo Juice** (2 tsp./Gal.) **Ultra Bloom** (1tsp./ Gal.) **BigBud** (100 ppms,)

OverDrive (100ppms) **Hygrozyme** (2tsp./Gal.) **Budswel** (3-6 tsp./Gal,) **Ooze Bloom** (1 tsp./Gal.,)

Vermi-T(1 Gal. per 50Gal) **BudCandy** (1-3tsp./Gal.)**MagiCal** (40ppm,) **Final Bloom** (1tsp. per Gal.,)

Roots Excel (1.1ml/Gal.), **Cannazym** (1-4tsp./Gal.,) **Roots Bloom** (1/2tsp./Gal.).

Week 1 TDS - 800 ppms - **Ultra Bloom** 1tsp./Gal. **Bud Candy** 2tsp./Gal.

Week 2 TDS - 900 ppms - Start **BigBud** - 100ppms

Week 3 TDS - 1000 ppms - **pH 5.8** Stop **Ultra Bloom**.. Start **Budswel** at 3 tsp./Gal. Last week of **Hygrozyme**.

Week 4 TDS - 1100 ppms - **pH 5.8** Start **Ooze Bloom** at 1 tsp./Gal. Stop **Hygrozyme**.

Week 5 TDS - 1200 ppms - Last week of **Big Bud**. Start **Cannazym** at 2tsp./Gal.

Week 6 TDS - 1300 ppms - **pH 5.7** Last week of **Ooze Bloom but use at 2 tsp./Gal**.. Stop using **Hygrozyme**.

Raise **Budswel** 6tsp./Gal. Stop using **BigBud**. Start **OverDrive** at 100 ppms.

Week 7 TDS - 700 ppms - **pH 5.6** Start **Purple Maxx** in Res at 1tsp./Gal. Take **Cannazym** up to 4tsp./Gal.

Raise **Bud Candy** up to 3tsp./Gal. No more **Ooze Bloom**..

Week 8 TDS - 0-300 ppms - **FLUSH** anywhere from 4-7 days to end of Harvest - Look below for instructions.

Note: You will be adding **BigBud, OverDrive, Ultra, Budswel, Hygrozyme, Ooze, and Bud Candy** for larger fruit / flowers throughout the Bloom phase. *If you ever see signs of stress then reduce the strength of these additives.* You will harvest anywhere from wks. 7-10 of Bloom. At that stage you will need to Flush. We suggest **Final Phase**. You can see that the general trend here is that you will be raising your TDS up from 1200 at week 1 all the way up to 1600 ppms by of the 6th week bloom. (Note that some plants need more than 8 weeks to create fruits/flowers - up to 10 weeks. Adjust accordingly.

Note: If at any point you see rust colored spotting, leaf tip burn, discoloration around leaf edges, yellowing of newer leaves, etc. check pH, check roots, lower TDS by 200-300. If it gets worse, drain / Flush Reservoir.

Working with Organics is a tricky endeavor. It can be very rewarding in the long run because your fruit/flowers will be more aromatic, have more flavor, and generally look very beautiful. That is why we are using this many additives in the reservoir. Each one is used for a specific duration, at a specific time to produce a specific effect. Pay close attention to your plants. And again --- If signs of nutrient burn are observed, lower TDS.

Here is an example of an eight-week bloom schedule: (Again the pH listings are for Hydro or Soiless not Soil.)

If Using SOIL adjust pH to 6.2 to 6.6 throughout all of Bloom Phase! Or Average of 6.5 pH

FLUSH - Use Final Phase. Make sure water comes out clean. "From Dirty to Clean"

Week 1 - TDS 1200 (pH 5.8, Start Ultra Bloom at 1tsp./Gal. Start Bud Candy at 2tsp./Gal.)

Drain and Refill Reservoir using **RO water**. Check water temp after 1 day. Make sure it is between 66-68 deg. F. Connect Air Stones to Air Pump and submerge Stones (Not Pump!) in Water, Making Sure Stones work.

Add **MagiCal** up to 30-40 ppms.

Add Additives. (**Vermi-T, Roots Bloom, Piranha, Hygrozyme, Voodoo Juice, Bud Candy, and Ultra Bloom.**)

Now add **Heavy 16** - bring TDS to 1200 ppms.

Adjust **pH** to **5.8** (Most Plants will now be at lower pH like 5.8) Soil pH should be btwn 6.2-6.6.

Make sure Tray(s) are draining completely. Make sure you **CONNECT** Irrigation PUMP to timer and it is ON!

: 3560 STATE STREET
: SANTA BARBARA, CA 93105
: PHONE: 805.898.9922
: FAX: 805.898.0047

: 2405 MIRA MAR AVE.
: LONG BEACH, CA 90815
: PHONE: 562.627.5636
: FAX: 562.627.1618

: 496 W. MEATS ST.
: ORANGE, CA 92865
: PHONE: 714.974.4769
: FAX: 714.921.4769

: 11510 WHITTIER BLVD.
: WHITTIER, CA 90601
: PHONE: 562.699.4201
: FAX: 562.699.7598

: © 2009 GCH, INC.
: www.gchydro.com
: info@gchydro.com
: TOLL FREE: 877.MY.HYDRO
: 69 49376



FLUSH - Plain RO Water - Make sure water comes out clean. "From Dirty to Clean"

Week 2 - TDS 1300 (Start adding **BigBud** at 100ppms.)

Fill Reservoir w/ **RO water**. Make sure Reservoir temperature is between 66-68 deg. F.

Add **MagiCal** up to 30-40 ppms.

Add Additives. (**Roots Excel, Piranha, Hygrozyme, Voodoo Juice, Big Bud, Bud Candy, and Ultra Bloom.**)

Now add **Heavy 16** and bring TDS up to 1300

Adjust pH to **5.8**. Soil pH should be btwn 6.2-6.6.

Keep levels of pH and TDS correct. Make sure you have good drainage!

FLUSH - Plain RO Water - Make sure water comes out clean. "From Dirty to Clean"

Week 3 - TDS 1400 (Stop **Ultra Bloom**..) (Start **Budswel** at 3 tsp./Gal. Last week of **Hygrozyme**.)

Drain and Refill Reservoir using **RO water**.

Check water temp after 1-2 days. Make sure it is 66-68 deg. F.

Connect Air Stones to Air Pump and submerge Stones (Not Pump!) in Water. Make Sure Stones work.

Add **MagiCal** up to 30-40 ppms.

Add Additives. (**Vermi-T, Roots Bloom, Hygrozyme, Budswel, Bud Candy, and BigBud.**)

Now add **Heavy 16** bringing TDS to 1400 ppms.

Adjust pH to **5.8**. Soil pH should be btwn 6.2-6.6.

Make Sure Roots are still healthy.

Make sure you CONNECT Irrigation PUMP to timer and it is ON! *Common mistake after draining reservoir.*

You should see good mychorizae growth from Piranha. White fuzzy healthy roots.

A critical stage of development. **Vermi-T** should be in Full Bloom. **Roots Excel** keeping the roots healthy.

FLUSH - Plain RO Water - Make sure water comes out clean. "From Dirty to Clean"

Week 4 - TDS 1500 (Start using **Ooze Bloom** at 1 tsp./Gal. Stop **Hygrozyme**.)

Fill Reservoir w/**RO Water**. Make sure Reservoir temperature is 66-68 deg. F.

Add **MagiCal** up to 30-40 ppms.

Add Additives. (**Roots Excel, Hygrozyme, Budswel, Big Bud, Bud Candy, and Ooze Bloom.**)

Now add **Heavy 16** and bring TDS up to 1500 ppms.

Adjust pH to **5.8**. Soil pH should be btwn 6.2-6.6.

Make sure you have good drainage! Roots can die easily from suffocation at this stage.

FLUSH - Use Final Phase. Make sure water comes out clean. "From Dirty to Clean"

Week 5 - TDS 1600. (Last week of **Big Bud**. Start **Cannazym** at 2 tsp./Gal.)

Start Your Reservoir by adding **RO water**.

Add Additives. (**Roots Bloom, Vermi-T, Hygrozyme, Cannazym, Budswel, Big Bud, Bud Candy, and Ooze Bloom.**)

Now add **Heavy 16** - bring TDS to 1600 ppm.

Adjust pH to **5.8**. Soil pH should be btwn 6.2-6.6.

Make sure Irrigation PUMP is connected to timer and that it is ON! Make sure Tray(s) are draining completely.

Make Sure Roots are still healthy. Almost at the home stretch!

Check water temp after 1-2 days. Make sure it is 66-68 deg. F.

FLUSH - Plain RO Water - Make sure water comes out clean. "From Dirty to Clean"

Week 6 - TDS 1600 (Raise **Budswel** to 6tsp./Gal. Stop **Big Bud**. Start **OverDrive** at 2tsp./Gal.

Raise **Ooze Bloom** to 2 tsp. / Gal. and note that it is the last week.)

Fill Reservoir w/ **RO water**. Make sure Reservoir temperature is between 66-68 deg. F.

No **BigBud** Anymore! Only **OverDrive**.

Add Additives. (**Roots Excel, Cannazym, Budswel, Big Bud, Bud Candy, and Ooze Bloom.**)

Check Water temp - it should be 66-68 deg. F.

Now add Grand Finale at 6 tsp./Gal. look out for advanced Yellowing. If needed add 300 ppms of Heavy 16.

Adjust pH to **5.7**. (This is down from last week where it was 5.8.) Soil pH should be btwn 6.2-6.6.

No **BigBud** Anymore!!! Only **OverDrive**!!!

: 3560 STATE STREET
: SANTA BARBARA, CA 93105
: PHONE: 805.898.9922
: FAX: 805.898.0047

: 2405 MIRA MAR AVE.
: LONG BEACH, CA 90815
: PHONE: 562.627.5636
: FAX: 562.627.1618

: 496 W. MEATS ST.
: ORANGE, CA 92865
: PHONE: 714.974.4769
: FAX: 714.921.4769

: 11510 WHITTIER BLVD.
: WHITTIER, CA 90601
: PHONE: 562.699.4201
: FAX: 562.699.7598

: © 2009 GCH, INC.
: www.gchydro.com
: info@gchydro.com
: TOLL FREE: 877.MY.HYDRO
: 69 49376



Look for signs of Nutrient Burn, Yellowing, Rust Color Spotting, Leaf tip burn. Only small amounts of this are acceptable at this stage. If you notice heavy damage, lower TDS 200 ppms, If damage continues, Flush and reduce TDS by 400ppms and lower strength of Additives - **Ooze Bloom, Overdrive, Budswel, Bud Candy.**

At this point fruit or flowers should be filling in rapidly and ripening is soon to begin.

Roots may be yellow or cream colored on mature plants. You should still have mycorrhizae white fuzz on your roots if using **Piranha**. Lower leaves can Yellow from a lack of Nitrogen.

FLUSH - Use RO Water. Make sure water comes out clean. "From Dirty to Clean"

Week 7 - TDS 1000(Start **Purple Maxx** in Res at 1tsp./Gal.) (Spray **Purple Maxx** Lightly 1tsp./Quart - Every Day!)
(Bring **Cannazym** up to 4tsp./Gal. Bring **Bud Candy** up to 3tsp./Gal. Stop **Ooze Bloom.**)

Start Your Reservoir by adding **RO water**

Connect Air Stones to Air Pump and submerge Stones (Not Pump!) in Water, Make Sure Stones work.

Add Additives. (**RootsBloom, Vermi-T, Cannazym, Budswel, Big Bud, Bud Candy, and Purple Maxx.**)

Now add **Grand Finale** at 4tsp./Gal.

Adjust **pH to 5.6**. Soil pH should be btwn 6.2-6.6.

Make sure Tray(s) and Pot(s) are draining completely.

Make Sure Roots are still healthy. If not, it should not matter that much, but try and do better NEXT time.

Make sure Irrigation PUMP is still connected to timer and it is ON!

Check water temp after 1-2 days. Make sure it is between 66-68 deg. F.

FLUSH - Use Final Phase. Make sure water comes out clean. "From Dirty to Clean"

Week 8 - (**FLUSH!**) - Lower Res Tempsto 50 deg. F. - NO NUTRIENTS!

Fill Reservoir w/ **RO water**. Make sure Reservoir temperature is as close to 50 deg. F.

Add Additives. (**Final Phase, Cannazym, Bud Candy, and PurpleMaxx.**)

Adjust **pH to 5.6** Soil pH should be btwn 6.2-6.6.

FLUSH --- either at the beginning of this week and ignore the above. Or after 3 days Flush for final 4 days. Read Flushing notes below.

Final Flushing:

To flush, drain reservoir 4-7 days from finish. Fill with fresh water. Add **Final Phase** at a rate of 2tsp. per Gallon. Add Nutrient. Raise TDS to 500 ppms. Run for 1-2 days. Drain Reservoir. Repeat process (add Final Phase) and run until fruit is ripe. One a day until last flush which runs for 2 days.

General Notes:

If at any point you see evidence of disease (persistent major pH shift, foamy / slimy-ness in the reservoir, large scale root death.) You will need to clean and sterilize the reservoir and trays. Flush out the pots and trays with a copious amount of water. Bleach as much of the hydro system as possible (including tubing, pump, reservoir and trays.) Bleach will kill diseases, but is also toxic to plants, so be sure to rinse well before reusing. Refill reservoir and re-dose. Be prepared to Flush the system every other day until the problem is solved.

It is also a good idea to wash out your reservoir monthly. On any one of the bi-weekly drains you can take it out and bleach it down. Then rinse it well to remove the bleach residue. When clean restart as normal.

Again, look for any signs of stress. Anything at all. If you see any discoloration, or any damage to the roots. Call us! Or, come in and talk with us about it! *We can help.* We can help - If its not too late!


Disclaimer

Individual results may vary. We are in no way responsible for your results. Environmental Conditions can change any end result. We are not responsible for other people's mistakes. This is a generalized recipe for tomatoes and cucumbers in particular. Use a TDS meter. Maintain pH. Maintain a Healthy Reservoir Temperature. Use RO water. Change Out Reservoir. Call us with problems. This recipe is intended for legal use only.



Overall Concentrations (TDS) - in ppms (w/a 700 Conversion Factor)

Heavy 16 BUD A+B as Main Nutrient



week 1	week 2	week 3	week 4	week 5	week 6	week 7	week 8
week 1 MagiCal 30-40 ppms Roots Bloom 1/2 tsp. / Gal. Vermi - T 1 Gal. / 50 Gal. Piranha 0.75grm./Gal. Voodoo Juice 2 tsp. / Gal. BigBud 2 tsp. / Gal. Ultra Bloom 1tsp. / Gal. Hygrozyme 2 tsp. / Gal. Bud Candy 2 tsp. / Gal.	week 2 MagiCal 30-40 ppms Roots Excel 1.1mL / Gal. Piranha 0.75grm./Gal. Voodoo Juice 2 tsp. / Gal. BigBud 100 ppms Hygrozyme 2 tsp. / Gal. Ultra Bloom 1tsp. / Gal. Bud Candy 2 tsp. / Gal.	week 3 MagiCal 30-40 ppms Roots Bloom 1/2 tsp. / Gal. Vermi - T 1 Gal. / 50 Gal. Budswel 3 tsp. / Gal. Ooze Bloom 1 tsp. / Gal. BigBud 100 ppms Hygrozyme 2 tsp. / Gal. Bud Candy 2 tsp. / Gal.	week 4 MagiCal 30-40 ppms Roots Excel 1.1mL / Gal. Budswel 3 tsp. / Gal. Ooze Bloom 1 tsp. / Gal. BigBud 100 ppms Hygrozyme 2 tsp. / Gal. Bud Candy 2 tsp. / Gal.	week 5 Roots Bloom 1/2 tsp. / Gal. Vermi - T 1 Gal. / 50 Gal. Ooze Bloom 1 tsp. / Gal. BigBud 100 ppms Cannazym 2 tsp. / Gal. Bud Candy 2 tsp. / Gal. Hygrozyme 2 tsp. / Gal. Budswel 3 tsp. / Gal.	week 6 Roots Excel 1.1mL / Gal. Ooze Bloom 2tsp. / Gal. OverDrive 100 ppms Cannazym 2 tsp. / Gal.. Bud Candy 2 tsp. / Gal. Budswel 6 tsp. / Gal.	week 7 Roots Bloom 1/2 tsp. / Gal. Vermi - T 1 Gal. / 50 Gal. OverDrive 100 ppms Cannazym 4 tsp. / Gal. Bud Candy 3 tsp. / Gal. Budswel 6 tsp. / Gal. Purple Maxx 1 tsp. / Gal.	week 8 Final Phase 2 tsp./Gal. Bud Candy 3tsp./Gal. Cannazym 4 tsp../Gal. Purple Maxx 1 tsp. / Gal.

5mL = 1teaspoon
 15mL= 1 Tablespoon = 3 teaspoons

3560 STATE STREET
 SANTA BARBARA, CA 93105
 PHONE: 805.898.9922
 FAX: 805.898.0047

2405 MIRA MAR AVE.
 LONG BEACH, CA 90815
 PHONE: 562.627.5636
 FAX: 562.627.1618

496 W. MEATS ST.
 ORANGE, CA 92865
 PHONE: 714.974.4769
 FAX: 714.921.4769

11510 WHITTIER BLVD.
 WHITTIER, CA 90601
 PHONE: 562.699.4201
 FAX: 562.699.7598

© 2009 GCH, INC.
 www.gchhydro.com
 info@gchhydro.com
 TOLL FREE: 877.MY.HYDRO
 69 4 9376

